

## Answer to Question#51244 – Physics – Solid State Physics

### Point defects

Point defects are defects that occur only at or around a single lattice point. They are not extended in space in any dimension. Strict limits for how small a point defect is are generally not defined explicitly, typically, however, these defects involve at most a few extra or missing atoms. Larger defects in an ordered structure are usually considered dislocation loops. For historical reasons, many point defects, especially in ionic crystals, are called centers: for example a vacancy in many ionic solids is called a luminescence center, a color center, or F-center. These dislocations permit ionic transport through crystals leading to electrochemical reactions. These are frequently specified using Kröger–Vink Notation.

### Line defects

Dislocations are linear defects around which some of the atoms of the crystal lattice are misaligned. There are two basic types of dislocations, the edge dislocation and the screw dislocation. "Mixed" dislocations, combining aspects of both types, are also common.

Edge dislocations are caused by the termination of a plane of atoms in the middle of a crystal.

The screw dislocation is more difficult to visualise, but basically comprises a structure in which a helical path is traced around the linear defect (dislocation line) by the atomic planes of atoms in the crystal lattice.

### Planar defects

#### Stacking Faults and Twin Boundaries

A disruption of the long-range stacking sequence can produce two other common types of crystal defects: 1) a stacking fault and 2) a twin region. A change in the stacking sequence over a few atomic spacings produces a stacking fault whereas a change over many atomic spacings produces a twin region.

A stacking fault is a one or two layer interruption in the stacking sequence of atom planes. Stacking faults occur in a number of crystal structures, but it is easiest to see how they occur in close packed structures. For example, it is known from a previous discussion that face centered cubic (fcc) structures differ from hexagonal close packed (hcp) structures only in their stacking order. If a stacking fault does not correct itself immediately but continues over some number of atomic spacings, it will produce a second stacking fault that is the twin of the first one. For example if the stacking pattern is ABABABAB but switches to ABCABCABC for a period of time before switching back to ABABABAB, a pair of twin stacking faults is produced. The red region in the stacking sequence that goes ABCABCACBACBABCABC is the twin plane and the twin boundaries are the A planes on each end of the highlighted region.